

NiCE IA & QC v12.5 Troubleshooting

NiCE Interaction Analytics & Quality Central v12.5

Global Education Services



NiCE Interaction Analytics & Quality Central
Troubleshooting Fundamentals – Exercise Book

Contents

1 – Ingest Flow & Search..... 2

2 – Ingest Troubleshooting Scenario..... 3

3 – Discovery Flow 3

4 – Discovery Troubleshooting Scenario..... 5


5 – Search Grid..... 5

6 – Playback Troubleshooting Scenario 6

7 – QC Troubleshooting Scenario 6

Environment

When you connect to a new lab, please run the Nexidia Configuration Manager and start all service on the NIA server.



1 – Ingest Flow & Search

This section follows the Ingest flow.

1. Stop the Nexidia Search Grid Agent Service located on the Grid3 server
2. Start the nexidia services in NIA server
3. Create a new session, point it to the "**Billing**" media folder, and select queries to apply to the interactions.
4. Stop the Nexidia Ingest Service located on the NIA server
5. How many interactions appear in the Source Media Inbox table (NexidiaESI DB)?
6. How many interactions appear in the Source Media table (NexidiaESI DB)?
7. What is the value of the 'Search Grid ID 'column in the Source Media table?
8. What is the value of the 'last ingest Session Tick' column in the Source Media Tick table?
9. Start the Ingest Service, login to the Session Status tab in the application, and run the session (click on the update result and reactivate the session option).
10. Start the Nexidia Search Grid Agent Service located on the Grid3 server

Session Status							
Start All Stop All Export Refresh							
NAME	VERSION	OWNER	STATUS	DATE FILTERS	STARTED	HOURS	FILES
EX1	1	superuser	Ingesting	[open] - [open]	10/4/2020 11:22:15 AM	00:00:00	0

- How many interactions appear in the Source Media table (NexidiaESI DB)?
- What is the value of the 'Search Grid ID 'column in the Source Media table?
- What is the value of the 'last ingest Session Tick' column in the Source Media Tick table?

2 – Ingest Troubleshooting Scenario

*ACME is a call center with NIA+QC. Steven Mills, who is working as a Team lead, needs to import all the calls in **TS1Lab** media folder in NIA. When he tried to do so, he was not able to find the “Session management” option in the administration menu. Make sure that he is able to import all calls in the media folder. If he is not able to do so, identify which calls were not imported and why?*

Credentials:

Username :smills

Password :password

You may need to reset the password. You can reset to the same “password”.

3 – Discovery Flow

This section follows the Ingest flow.

- Create TMS
- How many interactions appear in the 'TargetMediaSet.dimmapTargetMediaSetBridgeMediaFile ' table (Nexidia ESIDW)
- Navigate to the discovery application and set the TMS you created in the previous step for ASR, with a sample rate of 100%, do not select the "Active" checkbox, and save it.

SENTIMENT WORD CLOUD DASHBOARDS GAINERS & LOSERS

Media Set Administration

 Save

In the table below, click the Target Media Sets to sample, pick a sampling rate for each one and activate the Media Sets before clicking Save.

Target Media Set Name	Sample Rate	Active	Dispositioning Enabled	Phrase Pack	Phrase Group
TMS	100	☐	☐	Telco 0.0.0	phk

*Note: a Target Media Set will not automatically re-sample if it has been enabled previously.

*Note: Enabling a Target Media Set for query dispositioning will consume approximately 15GB per set. Avoid enabling dispositioning on overlapping  used for query building.

Create, edit or delete Target Media Set Phrase Groups using the table below. Only unused Phrase Groups are eligible for deletion.



Group name	Edit	Delete
1414		

- How many interactions appear in the **Source Media** table (NxDiscovery)
- Activate the TMS and save.
- Click on the Sentiment tab, in the Select Target Media set and filter window, select the TMS and set the date range to start from the year 2010; click ok

Select Target Media Set and Filters 

MEDIA SET  SAVED FILE SET

Currently selected media set: BillingTMS

(name contains)

BillingTMS 

☒ Date Range 10/31/2010  To 11/8/2022 

☐ Offset First 5 seconds

☐ Sentiment -50  50

+ Add More Filters...


Media Set Administration  

- How many interactions appear in the **Source Media** table (NxDiscovery)

4 – Discovery Troubleshooting Scenario

Steve mills received a report from his team about an issue when they tried to create a new TMS for the interactions in “**Billing**” media folder. They wanted to remove some phrases from the phrase group. When they tried to view the word cloud in Discovery application and the sentiment, they was not able to see any data.

But another TMS created for a “Billing” media folder was producing results. The report also mentioned that there is an error in the server status indicating a problem with the ingest service as below. Steven mills tried to verify that issue but he was not able to do so. Identify and fix the issues so that Steven mills and his team can see the discovery word cloud and resolve the problem with the ingest service.



5 – Search Grid

This section demonstrates the uses of the SG Management Console

1. Login to Grid 1 server, from the start menu, run the Search Grid Management console.
2. Login to SG Management Console with user admin & password admin
3. Run the get-tenant command. How many tenants are there in this Search Grid?
4. Run the get-systop command. This will show the locations of all the nodes.
5. Stop the Nexidia Search Grid Agent Service, run the test-sys command
6. Start the Nexidia Search Grid Agent Service, run the test-sys command

6 – Playback Troubleshooting Scenario

*Steven Mills is trying to review calls with his team which handles the “**Billing** calls”. He was reporting that he got some random playback issues. Make sure that he was able to playback all calls successfully.*

7 – QC Troubleshooting Scenario

*Peter Britt is logging into QC <http://nia/NxIA/Portal/Login.aspx> as "Agent" to view the Evaluation score card and the published evaluations in the date range **8/23/2025 - 8/29/2025**. He was able to view his Evaluation dashboard, but he could not see his individual evaluations. Identify and fix the issues so that Peter Britt can see his individual evaluations.*

Agent Credentials:

Username: pbritt

Password: nicecti

Evaluator Credentials:

Username: dvoss

Password: nicecti

LOGS:

Nexidia logs location: Located on the NIA server -> C:\ProgramData\Nexidia\Analytics

Discovery SG logs location: Located on Grid1 server-> D:\ProgramData\Nexidia\Search Grid

Phonetics SG logs location: Located on Grid2 server D:\ProgramData\Nexidia\Search Grid



Contact us: training@nice.com | Visit us: [NiCE Dojo](#)

PROPRIETARY AND CONFIDENTIAL INFORMATION

Information herein is proprietary and trade secrets of NiCE Ltd and/or its affiliated companies (Affiliates). This document and the information herein is the exclusive property of NiCE and its Affiliates and shall not be disclosed, in whole or in part, to any third party or utilized for any purpose other than the expressed purpose for which it has been provided.

IMPORTANT NOTICE

Subject always to any existing terms and conditions agreed between you and NiCE or any Affiliate with respect to the products which are the subject matter of this document, neither NiCE nor any of its Affiliates shall bear any responsibility or liability to a client or to any person or entity with respect to liability, loss or damage caused or alleged to be caused directly to, any interruption of service, loss of business or anticipatory profits or consequential damage resulting from the use or operation of any products supplied or the content of this document. Information in this document is subject to change without notice and does not represent a commitment on the part of NiCE or any Affiliate.

All information included in this document, such as text, graphics, photos, logos and images, is the exclusive property of NiCE or an Affiliate and is protected by the United States and international copyright laws. Permission is granted to use, view and photocopy (or print) materials from this document only in connection with the products to which this document relates and subject to the terms of license applicable to such products. Any other use, copying, distribution, retransmission or modification of the information in this document without the express prior written permission of NiCE or an Affiliate is strictly prohibited. In the event of any permitted copying, redistribution or publication of copyrighted material, no changes in, or deletion of, author attribution, trademark legend or copyright notice shall be made. Products supplied may be protected by one or more of the US patents listed at www.nice.com/Patents. For the full list of trademarks of NiCE and its Affiliates, visit www.nice.com/NiCE-Trademarks. All other marks used are the property of their respective proprietors. All contents of this document are Copyright © 2025 NiCE Ltd. All rights reserved.

nice.com

NiCE